

# Product Change Notice

**Product Model Name: Gx134 – Gx174**

**Date: April 2008**

**Reference ECO No: 18904**

## Reason for Change

This PCN announces the release of G134 – G174 library firmware version H06e. This firmware is available at no cost from Plasmon via the website [www.plasmontech.com](http://www.plasmontech.com).

## Description of Change

The following changes/features are incorporated into the new firmware release:

- Resolved the intermittent interference of the picker finger at the drive bezel during the error recovery process.
- The LOG SELECT error statistics page , 31H, will now clear as denoted by the SCSI specification.
- UDO2 drive cleaning capability added to maintenance menu.
- H06c introduced an erroneous error of 04-80-20 at the end of the LIB VERIFY test. The erroneous error is resolved.
- Increased the put force of the picker at the drive to alleviate the occurrence of stalled pickers which caused library recoveries.

## Firmware

To confirm the current firmware version using the front panel display menus, select menu 1 Library Status > 1 Config Information > 1 Unit Information. If the new firmware is installed the front panel displays: **H06B CPU = 3069, DSP = 3046, CPLD = 0004** in bold text.

The following table shows the release history of the G134 – G174 library firmware.

Code	ECO#	CPU	DSP	CPLD
H03	17044	3038	3032	Up to 0003
H04	17185	3040	3034	Up to 0003
H04a	17241	3046	3034	Up to 0003
H05a	17636	3053	3039	Up to 0004
H05d	17925	3056	3041	Up to 0004
H05e	18053	3057	3041	Up to 0004
H05f	18092	3058	3041	Up to 0004
H06	18460	3060	3043	Up to 0004
H06b	18571	3064	3043	Up to 0004
H06c	18750	3065	3043	Up to 0004
H06e	18904	3069	3046	Up to 0004

**Contact Information for Technical Questions:**

**Americas and Asia Pacific**

Plasmon Technical Support Team  
United States Calls: 1-877-585-6793  
International Calls: 1-719-593-4437  
Fax: 1-719-593-4192  
Email: [tech.support@plasmon.com](mailto:tech.support@plasmon.com)  
Internet: [www.plasmon.com](http://www.plasmon.com)

**Europe, Africa, and Middle East**

Plasmon Technical Support Team  
International Calls: +44 (0) 1763 262 963  
Fax: +44 (0) 1763 264 407  
Email: [support@plasmon.co.uk](mailto:support@plasmon.co.uk)  
Internet: [www.plasmon.com](http://www.plasmon.com)