

Product Change Notice

Product Model Name: Gx24 – Gx80

Date: April 2008

Reference ECO No: 18904

Reason for Change

This PCN announces the release of G24 – G80 library firmware version G05e. This firmware is available at no cost from Plasmon via the website www.plasmontech.com.

Description of Change

The following changes/features are incorporated into the new firmware release:

- Resolved the intermittent interference of the picker fingers at the drive bezel during the error recovery process.
- The LOG SELECT error statistics page , 31H, will now clear as denoted by the SCSI specification.
- UDO2 drive cleaning capability added to maintenance menu.
- G05c introduced an erroneous error of 04-80-20 at the end of the LIB VERIFY test. The erroneous error is resolved.
- Increased the put force of the picker at the drive to alleviate the occurrence of stalled pickers which caused library recoveries

Firmware

To confirm the current firmware version using the front panel display menus, select menu 1 Library Status > 1 Config Information > 1 Unit Information. If the new firmware is installed the front panel displays: **G05B CPU = 3069, DSP = 3047, CPLD = 0004** in bold text.

The following table shows the release history of the G24 – G80 library firmware.

Code	ECO#	CPU	DSP	CPLD
A000	Initial Release	3003	3004	Up to 0002
A001	16306	3004	3004	Up to 0002
A002	16335	3007	3006	Up to 0002
A003	16336	3009	3007	Up to 0002
G000	16397	3017	30016	Up to 0002
G00a	16417	3019	30016	Up to 0002
G00b	16461	3021	3018	Up to 0002
G01	16791	3026	3023	Up to 0002
G02	17044	3037	3031	Up to 0003
G03	17185	3039	3033	Up to 0003
G03a	17241	3045	3033	Up to 0003

Code	ECO#	CPU	DSP	CPLD
G04a	17636	3053	3038	Up to 0004
G04d	17925	3056	3040	Up to 0004
G04e	18053	3057	3041	Up to 0004
G04f	18092	3058	3040	Up to 0004
G05	18460	3060	3042	Up to 0004
G05b	18571	3064	3042	Up to 0004
G05c	18750	3065	3042	Up to 0004
G05e	18904	3069	3047	Up to 0004

Contact Information for Technical Questions:

Americas and Asia Pacific

Plasmon Technical Support Team
 United States Calls: 1-877-585-6793
 International Calls: 1-719-593-4437
 Fax: 1-719-593-4192
 Email: tech.support@plasmon.com
 Internet: www.plasmon.com

Europe, Africa, and Middle East

Plasmon Technical Support Team
 International Calls: +44 (0) 1763 262 963
 Fax: +44 (0) 1763 264 407
 Email: support@plasmon.co.uk
 Internet: www.plasmon.com